

# Table of Contents

**IPv4 plans**

**IP plans**

**Client types**

**Subnets**

Subnet plan

Segments

3

3

3

4

5

8



# IPv4 plans

IP plans are at the heart of each IP network. The first step after creating a [Client type](#) is the modeling of the IP plans.

## IPv4 Plans

Plan ...	Plan size	Description	# Subnet Ra...	Client type	Name
0	32	Custom subnets	0	YCE	Demo Client type
1000	24	YCE Loopback	256	DCvxlan	Demo Client type
1001	24	YCE PPP connections	64		
1002	24	YCE Loopback Customer	242		
1010	24	YCE Redundant Management	1		
1011	20	YCE Redundant Production	16		
1020	24	YCE Single Management	1		

NewDelete

## Subnets

Subnet name	# Seg	Subnet size	Start IP	End IP	Remark
PPP	64	30	0.0.0.0	0.0.0.255	



NewDelete

## Subnets Plans

SegmentsSubnet plans

Plan ID	Subnet name	Segment	Prefix	Start IP	End IP	Net mask	Remark
1001	PPP	0	30	0.0.0.0	0.0.0.3	255.255.255.252	
1001	PPP	1	30	0.0.0.4	0.0.0.7	255.255.255.252	
1001	PPP	2	30	0.0.0.8	0.0.0.11	255.255.255.252	
1001	PPP	3	30	0.0.0.12	0.0.0.15	255.255.255.252	
1001	PPP	4	30	0.0.0.16	0.0.0.19	255.255.255.252	
1001	PPP	5	30	0.0.0.20	0.0.0.23	255.255.255.252	
1001	PPP	6	30	0.0.0.24	0.0.0.27	255.255.255.252	

ReindexDelete

Within the current version of netYCE both  [IPv4](#) and  [IPv6](#) are supported.

# IP plans

IP plans are essentially supernets with a reference number and a subnet mask. The supernet will be divided into one or more subnets (segments). A [client](#) can have one or more supernets associated.

# Client types

Client type	Name
HYP1	Interhyp LAN
YCE	YCE Example database
C	Cable Service Provider
COG	Cognizant
BEL	Belastingdienst NL
VER	Verzion
A	UCL

An IP plan can be used with multiple clients. Changing an IP plan should be done with extreme caution. The client types section of the form will show the client types associated with the selected IP-plan.

## Subnets

Create IPv4 subnet range

IP Subnets

Layer 2

Step 1: Subnet name and size

IPv4 subnet name:\*

Subnet size:

Step 2: Subnet minimum offset

Minimum offset:\*

Step 3: Subnet maximum offset

Maximum offset:\*

Number of subnets possible in range: 16


Step 4: Subnet remark

Net remark:

Cancel

Save

With the subnets section of the form, the IP plans can be segmented.

Using the New button  sign the IP plan subnet add form is opened and one or more ip subnets can be added.

By default, the subnets will be added with a 24 bits subnet. This can be changed by typing the prefix, or using the arrows.


Each subnet must have a name. A good practice is to make a reference to the function of the subnet, such as management, voice, data, ppp etc. When needed a remark can be added.


With **Minimum offset** you can select the starting point of your (first) subnet.

With **Maximum offset** you select the end-point of your (last) subnet.

The offset fields are intentionally not editable, this makes sure that no crazy offsets can be chosen. To overcome lots of clicking when a big free space exists in the plan, create as big as possible Free ranges so that the first free offset is near the requested one. After creating the latter subnets you can remove the segments of the Free subnets.

## Subnet plan

In the Subnet plan tab, the subnet can be modeled. Here the Default-gateway, VLAN ID etc can be defined. By clicking  the IP subnetplan add form will be opened.



The image shows a web form titled "Create IPv4 subnet plan". It has a close button (X) in the top right corner. The form contains the following fields and options:

- IPv4 plan id:** A text input field containing "1001".
- IPv4 subnet name:** A text input field containing "PPP".
- Options (left column):**
  - ☒ Loopback
  - ☒ Gateway
  - ☒ Point-to-point
  - ☐ Four-corners
  - ☒ Vlan
    - ☒ range
    - ☐ fixed
- References (right column):**
  - Loopback reference:** An empty text input field.
  - Management reference:** An empty text input field.
  - ☐ range
  - ☐ fixed

At the bottom right, there are two buttons: "Cancel" (grey) and "Save" (orange).

## IP address offset

When adding an IP address parameter, netYCE will use an offset from the subnet address. When the subnet address is 192.168.0.0 with a netmask of 255.255.255.0 and the offset is 0.0.0.2 the

resulting address will be 192.168.0.2. When the offset is 0.0.0.-1 the resulting address will be the highest available address 192.168.0.254.

## Loopback

Loopback will add two parameters. The first is the offset of 0.0.0.0 which means 0 bits offset from the subnet IP and number two is a topology position of **L**. This topology position will be assigned to the port.

## Gateway

Gateway will add one parameter. An IP offset of 0.0.0.1

## Point-to-point

Point-to-point will add 8 parameters. two parameters will have an IP offset of 0.0.0.1 and two will have an IP offset of 0.0.0.2. Also topology positions A (left), B (right), N (north) and S (south) will be added.

## Four-corners

## Vlan

VLAN will add two parameters. The scope of the VLAN whether it should be Site specific, Client specific or Service specific. The other parameter is the VLAN template. Here a VLAN [configuration template](#) can be used.

When adding a VLAN, the user must make a choice whether to have a range or a fixed VLAN ID.

### Range

When choosing *Range*, two parameters will be added. The minimum- and maximum offset of the VLAN ID. The maximum offset must be higher than the minimum. The range is between 1 and 4094.

### Fixed

When choosing *Fixed*, one parameter will be added. This is the VLAN ID.

## Loopback reference

It is possible to make a named reference to the loopback address. This is useful when using [Service](#)

tasks. This allows you to specify IP ranges within the subnet to be assigned, giving the opportunity to skip certain addresses.

Create IPv4 subnet plan

IPv4 plan id:1070

IPv4 subnet name:loopback

☐ Loopback

☐ Gateway

☐ Point-to-point

☐ Four-corners

☐ Vlan

Loopback reference:loopback

Management reference:

☒ range

☐ fixed

Which will look like this:

Subnets Plans

SegmentsSubnet plans

Parameter	Key	Value	Description
<If_loopback>	offset	0.0.0.0	Loopback is subnet/32 IP address
<If_loopback>	topo_pos	L	Assign L-topology to port
<Vlan_template>	str	loopback	Vlan port template of vlan interface
loopback	offset	0.0.0.0	Loopback IP address in (/32) subnet
loopback	scope	Subnet	Loopback IP address must be unique in the subnet
loopback	topo_pos	L	Assign L-topology to port

NewDelete

When using this in the Service type, the reference 'loopback' can be used for IP address assignments. A partial service type is shown that does a locate on the subnet and address.



Management reference

In order to force a specific IP address (or range of addresses) it is possible to use a named reference. This reference can be used in the same way as the loopback reference.

Range

The Range will add the Scope parameter, the Topology parameter and a minimum- maximum offset parameter. The Topology parameter can't be modified. The Scope can be Site (default) and Global.

In the picture below, it is seen that the subnet range has been specified to start at 0.0.0.4 till 0.0.0.-1 (which means the last address minus 1).

Subnets Plans

Segments Subnet plans

Parameter	Key	Value	Description
<Vlan_id>	scope	Site	Vlan-id must be unique within its scope
<Vlan_id>	int	103	Fixed Vlan-id
<Vlan_template>	str	vlan	Vlan port-template of vlan-interface
Management	scope	Subnet	Assigned IP address must be unique in the subnet
Management	topo_pos	M	Assign M-topology to port
Management	min_offset	0.0.0.4	Lowest available IP address in subnet range
Management	max_offset	0.0.0.-1	Highest available IP address in subnet range

Now Delete

The service type shows a partial set of commands to use the reference.



The output of this partial service type is shown below. Where you see the last address is used according to the service type usage.



Fixed

The *Fixed* will add the *Scope* parameter, the *Topology* parameter and a fixed offset parameter. The Topology and Site parameter are the same as the Range setting.

Segments

When selecting a subnet in the *Subnets* section, all the subnets will be listed in the *Segments* section. Individual segments can be deleted. It is possible to delete multiple segments in one action, by selecting multiple entries.

Using the *Reindex* button it is possible re-index the segments for a continuous numbering starting at 0.

From:  
<https://labs-wiki.netyce.com/> - **Technical documentation**

Permanent link:  
[https://labs-wiki.netyce.com/doku.php/menu:design:ip\\_plans:ipv4\\_plans](https://labs-wiki.netyce.com/doku.php/menu:design:ip_plans:ipv4_plans)

Last update: **2022/05/20 16:12**